

## Global Mapper 16.1 Installation

(Current version is 16.1, build 04/20/2015)

**Uninstall all previous versions of Global Mapper before starting.**

### STEP 1

Download the version 16.1 installation packages and place locally on systems or on a network server share. <http://www.blumarblegeo.com/products/global-mapper-download.php>  
32-bit or 64-bit is available

### STEP 2

Log in to the local system with administrator privilege.  
Make sure your computer is connected to the web (for licensing).




### STEP 3

Install Global Mapper 16.1 taking all the defaults

### STEP 4

The software will launch, enter the order number found on the back of the service manager letter in the pop-up. Once entered Press **Register Me!**

2 pop ups will appear telling you you're registered and thanking you, Press **OK in both.**



### STEP 5 (Optional LiDAR module)

Obtain the License Key from Lukus Monette or Mike Dunn

### STEP 6 (Optional LiDAR module)

In Global Mapper: Go to **Help>Module Extension Manager**

Under **Built-In Modules** Check the Box next to LiDAR.

Press **OK**

The software will launch, enter the order number obtained in the pop-up. Once entered Press **Register Me!**

The screenshot illustrates the process of enabling the LiDAR module in Global Mapper v15.2. The main application window is titled "Global Mapper v15.2 (b052714) [64-bit] - REGISTERED". The "Help" menu is open, and the "Module/Extension License Manager..." option is selected. The "Extension/Add-In Module Manager" dialog is displayed, showing the "Built-In Modules" section with the "LiDAR" checkbox checked. Below this, the "Registered External Feature Extensions" section is empty. A registration pop-up window is shown in the foreground, titled "Global Mapper v15.2.2 (b052714) [64-bit] [+LiDAR]". It contains a warning icon and the message: "Successfully saved the license file to the following location: C:\ProgramData\GlobalMapper\LiDAR15\LiDAR.lic". The "OK" button in this pop-up is highlighted. The registration dialog in the background has the "Order ID from a Recent Purchase for Node-Locked Licensing" option selected, with the "Order Number" field empty. The "Register Me!" button is also highlighted.

### STEP 7 (Optional LiDAR module) To Turn the License back to the pool for other users.

In Global Mapper: Go to **Help>Module Extension Manager**  
Under **Built-In Modules** Uncheck the Box next to LiDAR.  
Press **Yes**

