

Global Mapper 18.X Installation

(Current version is 18.0.3, build 11/16/16)

Uninstall all previous versions of Global Mapper before starting.

STEP 1

Download the version 18.0 installation packages and place locally on systems or on a network server share. <http://www.bluemarblegeo.com/products/global-mapper-download.php>

32-bit or 64-bit is available

Note: You will have to create a Blue Marble account to download.

STEP 2

Log in to the local system with administrator privilege.

Make sure your computer is connected to the web (for licensing).

STEP 3

Install Global Mapper taking all the defaults

STEP 4

Register Global Mapper v18.0 (b111616) [64-bit]

Blue Marble GEOGRAPHICS
Mind the gap between world and map

If you have purchased a license for the software, please enter the order ID provided to you when you purchased the software below. By registering, you make available the full capabilities of the product.

If you choose to continue without registering, you will not be able to export data or load workspaces, you will be limited to loading a max of 4 data files at a time, and you will be forced to endure this nagging screen every time you run the software.

If you do not have a registration key but would like more information on how to obtain one, please visit:
<http://www.bluemarblegeo.com/>
or call in your order to +1-800-616-2725 (US and Canada) or 001-207-622-4622 (rest of the world)
or email Global Mapper sales at gmorders@bluemarblegeo.com.

License Type

Order ID from a Recent Purchase for Node-Locked Licensing
Order Number:

Connect to a Network License Server



Select a License (.lic) File Provided via Email

Request a 2-Week Trial License

Your Machine ID (Provide if Requested): 204747C66987


The software will launch, enter the order number found on the back of the service manager letter in the pop-up. Once entered Press **Register Me!**

2 pop ups will appear telling you you're registered and thanking you, Press **OK in both.**



STEP 5

You will notice in some cases GM has the toolbars stacked. Go to **View>Toolbars>Restore Default Toolbar Positions**



STEP 6 (Optional LiDAR module)

Note: Use the same license key provided for registering Global Mapper in next step.


In Global Mapper: Go to **Help>Module Extension Manager**

Under **Built-In Modules** Check the Box next to LiDAR.

Press **OK**

The manager will launch, enter the order number obtained in the pop-up. Once entered Press **Register Me!**

Hit **OK** on the Successful message, then **OK** on the Module manager.



Extension/Add-In Module Manager

